
RSKtools for Matlab access to RBR data

Table of Contents

Introduction	1
Installing	1
Examples of use	1
Working with profiles	3
Customizing plots	3
See RSKtools_vignette2	4
Future plans	4
About this document	5

RSKtools v2.0.0; RBR Ltd. Ottawa ON, Canada; support@rbr-global.com; 2017-07-06

Introduction

RSKtools provides some convenience functions for common data extraction (e.g. extracting profiles from a continuous dataset) and visualisation (plotting individual profiles). From this version on, we are expanding on our post-processing functions. For plans for future additions, see the Future plans section.

Installing

The latest stable version of RSKtools can be found at <http://www.rbr-global.com/support/matlab-tools>.

- Unzip the archive (to ~/matlab/RSKtools, for instance)
- Add the folder to your path inside matlab (addpath ~/matlab/RSKtools or some nifty GUI thing)
- type help RSKtools to get an overview and take a look at the examples.

Examples of use

A connection to the database must be made to work with an RSK file using RSKtools. This connection is made using the RSKopen() function. Note that RSKopen does not actually read the data, but reads a /thumbnail/ of the data, which is up to 4000 samples long. The structure returned after opening an RSK looks something like:

```
file = 'sample.rsk';
rsk = RSKopen(file)

rsk =
    dbInfo: [1x1 struct]
instrumentChannels: [7x1 struct]
channels: [7x1 struct]
epochs: [1x1 struct]
```

```
    schedules: [1x1 struct]
    deployments: [1x1 struct]
    instruments: [1x1 struct]
    appSettings: [1x1 struct]
    ranging: [7x1 struct]
    continuous: [1x1 struct]
    parameters: [1x1 struct]
    parameterKeys: [23x1 struct]
    thumbnailData: [1x1 struct]
    region: [762x1 struct]
    regionCast: [508x1 struct]
    profiles: [1x1 struct]
    log: {[7.3688e+05] 'sample.rsk opened using
RSKtools v1...']}
```

To read the actual data, we use the `RSKreaddata()` function. If given with one input argument (the variable name of the RSK structure) it will read the entire data set. Because RSK files can store a large amount of data, it may be preferable to read a subset of the data, specified using a start and end time (in Matlab datenum format, which is defined as the number of days since January 0, 0000).

```
t1 = datenum(2014, 05, 03);
t2 = datenum(2014, 05, 04);
rsk = RSKreaddata(rsk, 't1', t1, 't2', t2);
```

Note that the data structure can be found in the structure at:

```
rsk.data

ans =
    tstamp: [22346x1 double]
    values: [22346x7 double]
```

In this example, because the instrument is a "CTD"-type instrument, we can derive a new channel called Salinity. `RSKderivesalinity` adds the data to all the appropriate places (using the Practical Salinity Scale). The salinity calculation is performed by the [TEOS-10](http://teos-10.org/software.htm) package, which is available from <http://teos-10.org/software.htm>.

```
rsk = RSKderivesalinity(rsk);
rsk.channels.longName


ans =
Conductivity
ans =
Temperature
ans =
Pressure
ans =
Dissolved O##
ans =
Turbidity
ans =
PAR
ans =
Chlorophyll
ans =
Salinity
```

Working with profiles

Profiling loggers with recent versions of firmware contain the ability to detect and log profile "events" automatically; these are denoted as "downcasts" and "upcasts". The function `RSKreadprofiles()` extracts individual profiles from the raw data, based on the previously identified profiling events. Then, quick plots of the profiles can be made using the `RSKplotprofiles()` function.

If profiles have not been detected by the logger or Ruskin. The function `RSKfindprofiles()` can be used. The `pressureThreshold` argument, which determines the pressure reversal required to trigger a new profile, and the `conductivityThreshold` argument, which determines if the logger is out of the water, can be adjusted for short or fresh water profiles.

```
% load the second to tenth profiles in both directions (upcast and  
downcast)  
rsk = RSKreadprofiles(rsk, 'profile', 2:10, 'direction', 'both');  
rsk = RSKderivesalinity(rsk);  
  
% plot the upcasts of Conductivity, Temperature and Salinity  
handles = RSKplotprofiles(rsk, 'channel',  
    {'conductivity', 'temperature', 'salinity'}, 'direction', 'up');
```



Customizing plots


All plotting functions return a handle which enables access to the lines in the plot. The output is a matrix containing a column for each channel subplot and a row for each profile.

handles

```
% To increase the linewidth of the first profile in all subplots  
(set(handles(1,:),{'linewidth'},{5}));
```

```
handles =  
9x3 Line array:
```

Line	Line	Line
Line	Line	Line
Line	Line	Line
Line	Line	Line
Line	Line	Line
Line	Line	Line
Line	Line	Line
Line	Line	Line
Line	Line	Line



See RSKtools_vignette2

A second vignette is available for information on getting started with post-processing functions.

Future plans

- Function to write metadata, log and data to a file.

- Wave processing functions.
- A TS plotting function.

About this document

This document was created using [Matlab™ Markup Publishing](#). To publish it as an HTML page, run the command:

```
publish('RSKtools_vignette.m');
```

See `help publish` for more document export options.

Published with MATLAB® R2015b