RSKtools for Matlab access to RBR data

Table of Contents

ntroduction	1
nstalling	1
Examples of use	
Vorking with profiles	
Customising plots	
ee RSKtools_vignette2	
ruture plans	
About this document	

RSKtools v2.0.0; RBR Ltd. Ottawa ON, Canada; support@rbr-global.com; 2017-07-07

Introduction

RSKtools provides some convenience functions for common data extraction (e.g., extracting profiles from a continuous dataset) and visualisation (e.g., plotting individual profiles). New in v2.0.0 are a suite of functions to perform routine processing steps to enhance the data quality (see RSKtools_vignette2 for more information). From this version on, we are expanding our data post-processing suite. See the Future Plans for some ideas, and please feel free to make suggestions.

Installing

The latest stable version of RSKtools can be found at http://www.rbr-global.com/support/matlab-tools.

- Unzip the archive (to ~/matlab/RSKtools, for instance)
- Add the folder to your path from the command line (addpath ~/matlab/RSKtools) or launch the path editor gui (pathtool).
- type help RSKtools to get an overview and take a look at the examples.

Examples of use

A connection to the database must be made to work with an RSK file using RSKtools. This connection is made using the RSKopen() function. Note that RSKopen does not actually read the data, but reads a /thumbnail/ of the data, which is up to 4000 samples long. The structure returned after opening an RSK looks something like:

```
instrumentChannels: [7x1 struct]
             channels: [7x1 struct]
               epochs: [1x1 struct]
            schedules: [1x1 struct]
          deployments: [1x1 struct]
          instruments: [1x1 struct]
          appSettings: [1x1 struct]
              ranging: [7x1 struct]
           continuous: [1x1 struct]
           parameters: [1x1 struct]
        parameterKeys: [23x1 struct]
        thumbnailData: [1x1 struct]
               region: [762x1 struct]
           regionCast: [508x1 struct]
             profiles: [1x1 struct]
                  log: {[7.3688e+05]
                                       'sample.rsk opened using
RSKtools v2...'}
```

To read the actual data, use the RSKreaddata function. If given with one input argument (the variable name of the RSK structure) it will read the entire data set. Because RSK files can store a large amount of data, it may be preferable to read a subset of the data, specified using a start and end time (in Matlab datenum format, which is defined as the number of days since January 0, 0000).

```
t1 = datenum(2014, 05, 03);
t2 = datenum(2014, 05, 04);
rsk = RSKreaddata(rsk, 't1', t1, 't2', t2);
```

Note that the logger data can be found in the structure at:

```
rsk.data
ans =
    tstamp: [22346x1 double]
    values: [22346x7 double]
```

In this example, because the instrument is a "CTD"-type instrument, Practical Salinity can be derived from conductivity, temperature, and pressure. RSKderivesalinity is a wrapper for the TEOS-10 GSW function gsw_SP_from_C, and it adds a new channel called Salinity as a column in rsk.data.values. The TEOS-10 GSW Matlab toolbox is freely available from http://teos-10.org/software.htm.

```
rsk = RSKderivesalinity(rsk);
rsk.channels.longName


ans =
Conductivity
ans =
Temperature
ans =
Pressure
ans =
Dissolved O2
ans =
Turbidity
ans =
```

```
PAR
ans =
Chlorophyll
ans =
Salinity
```

Working with profiles

Profiling loggers with recent versions of firmware contain the ability to detect and log profile "events" automatically; these are denoted as "downcasts" and "upcasts". The function RSKreadprofiles extracts individual profiles from the raw data, based on the previously identified profiling events. Then, plots of the profiles can be made using the RSKplotprofiles function.

If profiles have not been detected by the logger or Ruskin, the function RSKfindprofiles can be used. The pressureThreshold argument, which determines the pressure reversal required to trigger a new profile, and the conductivityThreshold argument, which determines if the logger is out of the water, can be adjusted to improve profile detection when the profiles are very shallow, or the water is very fresh.



Customising plots


All plotting functions return a handle which enables access to the lines in the plot. The output is a matrix containing a column for each channel subplot and a row for each profile.

```
handles
```

```
% To increase the linewidth of the first profile in all subplots
set(handles(1,:),{'linewidth'},{5});
handles =
```

```
nandies = 9x3 Line array:
```

Line	Line	Line
Line	Line	Line



See RSKtools_vignette2

A second vignette is available for information on getting started with post-processing functions.

Future plans

- Function to write metadata, log and data to a file.
- Wave processing functions.
- Function to plot temperature-salinity diagrams.

About this document

This document was created using MatlabTM Markup Publishing. To publish it as an HTML page, run the command:

```
publish('RSKtools_vignette.m');
```

See help publish for more document export options.

Published with MATLAB® R2015b